在英文 Windows 8 系統上使用支票通,如何可正常顯示中文

1. 如果大家使用英文 Windows 8 來執行支票通,當輸入中文時,在預設的情況下,只會顯示「??」的亂碼,(圖1)。以下教大家解決的方法。

Change Lang	Backup Data	Add Payee	Printer Setup	Begister	Order Form	Ext
Cheque Express Lit	te v.5.7				Reg Code :	1597202764.57
Choose Bank :	ABN AMRO Bank	k		- 0	Date: 2	3-07-2013
Cheque Number :	000001	- 	A/C Payee Only	Or Bearer Do	n't Print Amount	Don't Print Date
Bay to :	2					
		_)				-
\sim		/				
		/				· ·
Amount :		0.0	0 @ English Cu	rrency Chinese	Currency C Dig	it Currency
Amount :	E Candidate Words	0.0	0 (* English Cu	rrency Chinese	Currency C Di	tit Currency
Amount :	Candidate Words	0.0	0 🕫 English Cu	rrency C Chinese	Currency C Dig	jit Currency
Amount :	Candidate Words	0.0	0 (* English Cu	rrency Chinese	Currency C Dig	jit Currency
Amount :	Candidate Words Candidate Word	0.0	0 © English Cu	mency Chinese	Currency C Dig	pit Currency
Amount :	Candidate Words Candidate Word	0.0	0 © English Cu	rrency Chinese	Currency Di	jit Currency
Amount : Remark :	Candidate Words Candidate Words 1 DR	0.0	0 @ English Cu	rrency Chinese	Currency Di	jit Currency
Amount : Remark : Cheque History () Date	を Candidate Words 1 期 へ 2 編 3 報 4 略 5 週 6 週 7 触	0.0	0 @ English Cu	rrency Chinese	Currency Di	jit Currency
Amount : Remark : Cheque History ()	Candidate Words 1 59 2 46 3 46 5 38 6 55 7 46 8 46	0.0	0 @ English Cu	rrency Chinese	Currency Dig	git Currency

2. 先進入「Control Panel」,再選「Region」(圖 2)



開啟「Region」視窗後,進入「Administrative」的頁面,按下方的「Change system locale」
 (圖 3)。

l.	Region
ormats	_ocation Administrative
Welcor	ne screen and new user accounts
View syste	and copy your international settings to the welcome screen, m accounts and new user accounts.
	Copy settings
Langua	ge for non-Unicode programs
This s displa	etting (system locale) controls the language used when sying text in programs that do not support Unicode.
Curre	nt language for non-Unicode programs:
Er	nglish (United States)
	Change system locale
20°7 L	

4. 之後將「Current system locale」改為「Chinese (Traditional, Hong Kong SAR)(圖 4)。

Region Settings					
Select which language (system locale) to programs that do not support Unicode. accounts on the computer. Current system locale: Chinese (Traditional, Hong Kong SAR)	use when displaying text in This setting affects all user OK Cancel	¥			

5. 之後系統要求重新啟動,只要按「Restart now」即可(圖 5)。



6. 重新啟動 Windows 8 後,再執行支票通系統,已經可以正常輸入及顯示中文字了(圖 6)。

9	Cheque E	xpress Lite v.5.	7 Demo : only	50 cheques can	be printed !			
<u>C</u> hange Lang	Backup Data	Add Payee	Printer Setup	Register	Order Form	<u>E</u> xit		
Cheque Express Lite v.5.7 Reg Code : 159720276-L57								
Choose Bank :	ABN AMRO Bank			- C	Date :	23-07-2013	1	
Cheque Number :	000001		A/C Payee Only	Or Bearer Do	n't Print Amount	Don't Print Dat	u te	
Pay to :	陳大文					🖆	1	
		\nearrow				A	-	
A mount :		12 245 00		0.00		<u>×</u>		
· mount ·	 	12,343.00 五元整	English Ci	arrency (• Chinese	Currency ODi	git Currency		
Remark :						•		
			۶ 🔒	😂 🗙		×		
Cheque History (Read Only)		1					
Date	Cheque No.	Bank Name		Payee	Amount	Remark	^	
							-	